

# Intel Pro1000 LAN & Appstore

Beitrag von „Komander2011“ vom 7. Juni 2012, 22:29

naja das bekomm ich irgendwann schon hin..solange such ich mir eben die apps aus dem internet raus 😊

vielleicht kommt ja griven bald, der hat bestimmt was im sinn was es sein kann...ich bin schon lange am ende meines wissens was das thema angeht...

Edit:

INTEL PRO/VE 10/100

Open terminal:

Type:

sudo

vi

/System/Library/Extensions/IONetworkingFamily.kext/Contents/PlugIns/AppleIntel825x.kext/Contents/Info.pl

You will be prompted to enter your password. Enter it and press ENTER.

Press down arrow key to move your cursor and you will find something like the following.

```
<key>IOPCIMatch</key>
```

```
<string>0x10518086 0x10508086 0x10298086 0x10308086&0xfff0ffff 0x12098086  
0x12278086 0x12288086 0x12298086 0x24498086 0x24598086 0x245d8086 0x10918086  
0x10608086&0xfff0ffff</string>
```

In vi mode you can move your cursor up and down, or right and left using J(down), K(up), H(left) and L(right) or the arrow keys.

To insert, press 'I' key and now you are in inserting mode, now write your ID.

Insert your device ID and venderID next to: 0x10298086

Because: hardware ID is 1092 and venderID is 8086.

Intel Pro VE 10/100 is: 0x10928086

VI mode is line by line so you will need use your arrow keys to move into position.

If done, then press 'ESC' key to exit from inserting mode.

Press your arrow key down until you reach the end of all text.

Type the following without ' or ': ':wq!'

This saves and exits vi mode.

Use 'X' key to delete letters or write ':q!' to quit vi mode unsaved.

Write the following line on Terminal to clear kext cache.

```
rm /System/Library/Extensions.*
```

Quit Termunal.

Open DiskUtility and perform permission repair.

Reboot your machine.

Manual Permissions Repair:

```
sudo -s
```

```
<password>
```

```
cd /System/Library/Extensions/
```

```
chmod -R 755 IONetworkingFamily.kext
```

chown -R root:wheel IONetworkingFamily.kext

Additionally, delete Extensions.kextcache and Extensions.mkext.

Reboot.

<http://www.hackint0sh.org/off-...00-ve-mac-os-x86-1860.htm></address>

</address>hab ich probiert, geht auch nicht...im bios steht die karte auf enabled, systeminfo sagt mir, die karte ist da! id und alles hab ich...aber ich bekomme sie nicht zum laufen...habe schon fast alles probiert und keinen erfolg...</address>

</address> :help: :help: :help: kann jemand helfen??</address>